

OpcPropertyValue<T> Members

Namespace: Opc.UaFx

Assemblies: Opc.UaFx.Advanced.dll, Opc.UaFx.Advanced.dll

The [OpcPropertyValue<T>](#) type exposes the following members.

Constructors

OpcPropertyValue(T)

Initializes a new instance of the [OpcPropertyValue`1](#) class using the **value** specified.

C#

```
public OpcPropertyValue(T value)
```

Parameters

value T

The value of the property value represented.

OpcPropertyValue(T, DateTime)

Initializes a new instance of the [OpcPropertyValue`1](#) class using the **value** and **timestamp** specified.

C#

```
public OpcPropertyValue(T value, DateTime timestamp)
```

Parameters

value T

The value of the property value represented.

timestamp DateTime

The time stamp of the property value.

OpcPropertyValue(T, DateTime, OpcStatus)

Initializes a new instance of the [OpcPropertyValue`1](#) class using the **value**, **timestamp** and **status** specified.

C#

```
public OpcPropertyValue(T value, DateTime timestamp, OpcStatus status)
```

Parameters

value [T](#)

The value of the property value represented.

timestamp [DateTime](#)

The time stamp of the property value.

status [OpcStatus](#)

The status associated with the property value.

OpcPropertyValue(T, DateTime, OpcStatusCode)

Initializes a new instance of the [OpcPropertyValue`1](#) class using the **value**, **timestamp** and **statusCode** specified.

C#

```
[CLSCompliant(false)]
public OpcPropertyValue(T value, DateTime timestamp, OpcStatusCode statusCode)
```

Parameters

value [T](#)

The value of the property value represented.

timestamp [DateTime](#)

The time stamp of the property value.

statusCode [OpcStatusCode](#)

The [OpcStatusCode](#) form that the [OpcStatus](#) associated with the property value is derived.

Table of Contents

Constructors	1
OpcPropertyValue(T)	1
OpcPropertyValue(T, DateTime)	1
OpcPropertyValue(T, DateTime, OpcStatus)	1
OpcPropertyValue(T, DateTime, OpcStatusCode)	2

