

Rfc1006IPEndPoint Constructor

Overload List

---	Name	Description
	Rfc1006IPEndPoint(Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(Int32, Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.
	Rfc1006IPEndPoint(Int32, String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.
	Rfc1006IPEndPoint(IPAddress, Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(IPAddress, String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(String, Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(String, String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>remoteTSAP</i> and <i>localTSAP</i> information and the DefaultPort .
	Rfc1006IPEndPoint(IPAddress, Int32, Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.
	Rfc1006IPEndPoint(IPAddress, Int32, String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.
	Rfc1006IPEndPoint(String, Int32, Byte[], Byte[])	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.
	Rfc1006IPEndPoint(String, Int32, String, String)	Initializes a new instance of the Rfc1006IPEndPoint class using the specified <i>address</i> , <i>port</i> , <i>localTSAP</i> and <i>remoteTSAP</i> information.

[Top](#)

See Also

Reference

[Rfc1006IPEndPoint Class](#)

Rfc1006LibNet.Advanced Namespace

Table of Contents

Overload List	1
See Also	1
Reference	1

